

# Table of Contents

***Licensed Nodes*** ..... 3



# Licensed Nodes

Polling status:

Hostname	License	# licensed nodes: 13 Max # nodes in license: 15
clone_switch12	no	
router16	no	
router15	no	
renamedswitch5	no	
node1	no	
lab1data001core01	no	
lab1data001aggr02	no	
lab1data001aggr01	no	
lab1data001acc002	no	
lab1data001acc001	no	
jeroenktestdevice	no	
clone_switch2	yes	
clone_switch14	yes	
switch3	no	
fg-fw-01	no	switch3
clone_switch9	yes	
fake_switch13	yes	
switch4	yes	
switch9	yes	
hpe	yes	
core	no	
access2	no	
access1	no	

1 - 36 of 36 items

License on License off Search

Your netyce license contains a number of nodes that you will be able to use for compliance. When your actual amount of nodes exceeds this number, this form can be used to tweak which nodes you want to have activated.

The grid here contains all nodes in the NCCM. The colors correspond to their nccm status:

- **Black** means a node that is currently being polled
- **Red** means that polling on the node has been halted, due to an error (and it exceeded its maximum number of retries in its polling group)
- **Gray** means that the node is not currently polling for NCCM, it has been manually turned off.

The second column of the grid shows if the node is currently licensed. You can select one or more nodes, and turn their licenses on or off. Left of the grid, you can see how many licensed nodes you are, and the upper limit on the number of licensed nodes for your environment.

A few notes about licenses:

- If a node is added and you have not reached the maximum of licensed nodes, it will automatically be licensed.
- If a node is added and you have reached the maximum of licensed nodes, it will automatically be not licensed.
- When you enable one or more nodes for compliance, and the total amount of licensed nodes would exceed the maximum number of licensed nodes, a number of nodes are automatically set to not licensed, until it is no longer exceeded. It will start with the nodes with the polling time furthest into the future, that you did not select. After that it will continue with the nodes you selected, based on the same criteria. Your maximum number of licensed nodes can never be exceeded.

From:  
<https://wiki.netyce.com/> - **Technical documentation**

Permanent link:  
<https://wiki.netyce.com/doku.php/menu:cmpl:licences>

Last update: **2021/10/22 06:12**

